

APDU-Test Card Functional Requirements

Autor Andreas Schwier

Version V1.1

Datum 03. January 2012

APDU-Test Card Functional Requirements



© Copyright 2012 CardContact Software & System Consulting

The authors of this documentation make no representation or warranty regarding whether any particular physical implementation of any part of these specifications does or does not violate, infringe, or otherwise use the patents, copyrights, trademarks, trade secrets, know-how, and/or other intellectual property of third parties, and thus any person who implements any part of these specifications should consult an intellectual property attorney before any such implementation.



Content

| 1 | Overview | .4 |
|-------|-----------------------|-----|
| 2 | Card Configuration | .4 |
| 2.1 | Answer to Reset (ATR) | .4 |
| 3 | Commands | .5 |
| 3.1.1 | SELECT | . 5 |
| 3.1.2 | Case 1 Test | .6 |
| 3.1.3 | Case 2 Test | .6 |
| 3.1.4 | Case 3 Test | .7 |
| 3.1.5 | Case 4 Test | .8 |
| 3.1.6 | GET INFO | .8 |
| | | |

Revisions

| Datum | Bearbeiter | Änderungen | Version |
|------------|-----------------|--|---------|
| 18.11.2011 | Andreas Schwier | Initial Version for Public Release | 1.0 |
| 03.01.2012 | Andreas Schwier | Removed requirement FX.CAS2.2 and FX.CAS4.2 to allow zero sized card objects | 1.1 |



1 Overview

The APDU-Test Card implements four test APDUs, one for each case and each supporting short or extended APDUs. Each APDU implements a deterministic behaviour that allows testing the communication path between a test application and the test card.

2 Card Configuration

2.1 Answer to Reset (ATR)

During a reset the card answers with the ATR

3B FE 18 00 00 81 31 FE 45 80 31 81 54 48 53 4D 31 73 80 21 40 81 07 FA

which has the following meaning:

| Element | Content | Meaning |
|---------|------------|---|
| TS | 3B | Direct logic |
| TO | FE | TA1, TB1, TC1, TD1 present |
| | | 14 Historical bytes |
| TA1 | 18 | Clock conversion rate 372 |
| | | Maximum frequency 5 MHz |
| | | Bit rate conversion factor 12 |
| TB1 | 00 | Deprecated |
| TC1 | 00 | Extra guard time |
| TD1 | 81 | TD2 present |
| | | T=1 |
| TD2 | 31 | TA3, TB3 present |
| | | T=1 |
| TA3 | FE | Information field size 254 |
| TB3 | 45 | Character waiting time 43 etu |
| | | Block waiting time 15371 etu |
| HB1 | 80 | Category indicator |
| HB2-3 | 3181 | Card service data byte |
| | | - Application selection by full DF name |
| | | - No EF.DIR / EF.ATR access service |
| | | - Card without MF |
| HB4-8 | 5448534D31 | Card issuer data |
| | | - "HSM1" |
| HB9-12 | 73802140 | Card capabilities |
| | | - DF selection by full DF name |
| | | - Proprietary write |
| | | - Data unit 8 bit |
| | | - Command chaining supported |
| | | - Extended Lc und Le fields |
| | | - No logical channel |
| HB13-14 | 8107 | Life Cycle Operational State |
| TCK | FA | XOR of T0 to HB14 |

Table 1 - Answer to Reset

The card supports T=1 on the contact interface and T=CL on the contactless interface.

Andreas Schwier 4 / 9



3 Commands

3.1.1 SELECT

The SELECT APDU allows the terminal to select the APDU-Test applet on the card. The application is identified by the application identifier:

E8 2B 06 01 04 01 81 C3 1F 02 02

The aid represents the object identifier

iso(1) org(3) dod(6) internet(1) private(4) enterprise(1) CardContact(24991) iso7816(2) apdutest (2)

For selecting the application on the card, the following APDU shall be used:

| CLA | '00' | |
|--------|---------|---|
| INS | 'A4' | SELECT |
| P1 | '04' | Select application DF |
| P2 | '04' | Return File Control Parameter (FCP) |
| Lc | '0B' | |
| C-Data | AID | Application identifier as defined above |
| Le | '00' | |
| R-Data | FCP | File control parameter as defined below |
| SW1/2 | '90 00' | Normal processing |
| | '6A 82' | Applet not found |

Table 2 - SELECT APDU for the Applet

The following file control parameters are returned when selecting the application:

| Tag | | Len | Value |
|------|------|------|--|
| '62' | | | File Control Parameter |
| | '82' | '01' | '78' – shareable DF |
| | '85' | '02' | Major Minor version number |
| | '89' | '05' | The transmission parameter as defined in Table 4 |

Table 3 - File Control Parameter for SELECT application

In tag '89' the card transmits the current communication parameter:

| Offset | Length | Content |
|--------|--------|--|
| 0 | 1 | Media interface and active protocol |
| | | 0x - Contact interface 8x - Contactless Type A 7x - Contactless Type B 6x - USB x0 - T=0 x1 - T=1 or T=CL |
| 1 | 2 | Information Field Size for ICC (IFSC) |
| 3 | 2 | Information Field Size for Interface Device (IFSD) |

Table 4 – Transmission parameter

/FR.SELA.1/ The system must select the application and return in R-Data the file control parameter and SW1/SW2 = '90 00' - Normal processing.

Andreas Schwier 5 / 9



3.1.2 Case 1 Test

The Case 1 Test command expects the reader to transmit a Case 1 APDU as defined in [ISO7816-3]. The APDU only returns SW1/SW2, but no response data.

| CLA | '80' | |
|--------|---------|----------------------------|
| INS | 'F1' | Case 1 APDU Test |
| P1 | '00' | |
| P2 | '00' | |
| Lc | Absent | |
| C-Data | Absent | |
| Le | Absent | |
| R-Data | Absent | |
| SW1/2 | '90 00' | Normal processing |
| | '67 00' | Wrong length |
| | '6A 86' | Incorrect parameters P1-P2 |

Table 5 - Case 1 Test APDU

/FR.CAS1.1/ The system must respond with empty R-Data and SW1/SW2 = '90 00' - Normal processing.

3.1.2.1 Exception Handling

| /FX.CAS1.1/ | If the C-Data field is present, then the system must respond with empty R-Data |
|-------------|--|
| | and SW1/SW2 = '67 00' - Wrong length. |

/FX.CAS1.2/ If the P1 field does not contain '00' or the P2 field does not contain '00', then the system must respond with empty R-Data and SW1/SW2 = '6A 86' - Incorrect parameters P1-P2.

3.1.3 Case 2 Test

The Case 2 Test command transmits to the reader the number of bytes requested in Ne, based on a card object with the size defined by P1 and P2.

| CLA | '80' | |
|--------|---------|---|
| INS | 'F2' | Case 2 APDU Test |
| P1 | Var | MSB of card object size |
| P2 | Var | LSB of card object size |
| Lc | Absent | |
| C-Data | Absent | |
| Le | Var | Ne encoded in short or extended format |
| R-Data | Var | The requested number of bytes which is a repeating sequence of the bytes 'A55A0000FFFFCAFEBABE' |
| SW1/2 | '90 00' | Normal processing |
| | '62 82' | End of file reached before reading Ne bytes. |
| | '67 00' | Wrong length |

Table 6 - Case 2 Test APDU

Andreas Schwier 6 / 9



- /FR.CAS2.1/ The system must respond with the requested number of bytes build from the reference string in R-Data and SW1/SW2 = '90 00' Normal processing.
- /FR.CAS2.2/ If Ne is not 0 and requests more data than is actually available based on the definition in P1 and P2, then the system must respond with the available data in R-Data and SW1/SW2 = '62 82' End of file reached before reading Ne bytes.

3.1.3.1 Exception Handling

/FX.CAS2.1/ If the C-Data field is present, then the system must respond with empty R-Data and SW1/SW2 = '67~00' - Wrong length.

3.1.4 Case 3 Test

The Case 3 Test command transmits arbitrary data to the card. The received data is silently discarded.

| CLA | '80' | |
|--------|---------|--|
| INS | 'F3' | Case 3 APDU Test |
| P1 | '00' | |
| P2 | '00' | |
| Lc | Var | Nc encoded in short or extended format |
| C-Data | Var | Arbitrary data with the length encoded in Nc |
| Le | Absent | |
| R-Data | Absent | |
| SW1/2 | '90 00' | Normal processing |
| | '67 00' | Wrong length |
| | '6A 86' | Incorrect parameters P1-P2 |

Table 7 - Case 3 Test APDU

/FR.CAS3.1/ The system must accept arbitrary data in C-Data and respond with empty R-Data and SW1/SW2 = '90 00' – Normal processing.

3.1.4.1 Exception Handling

| /FX.CAS3.1/ | If the C-Data field is missing, then the system must respond with empty R-Data and SW1/SW2 = '67 00' - Wrong length. |
|-------------|--|
| /FX.CAS3.2/ | If the P1 field does not contain '00' or the P2 field does not contain '00', then the |

system must respond with empty R-Data and SW1/SW2 = '6A 86' - Incorrect parameters P1-P2.

/FX.CAS3.3/ If the number of bytes transmitted in C-Data field does match Nc, then the system must respond with empty R-Data and SW1/SW2 = '6A~80' - Incorrect parameters in the command data field.

Andreas Schwier 7 / 9



3.1.5 Case 4 Test

The Case 4 Test command transmits arbitrary data to the card and responds with the number of bytes requested in Ne. The received data is silently discarded and the transmitted data is as defined for the Case 2 Test.

| CLA | '80' | |
|--------|---------|---|
| INS | 'F4' | Case 4 APDU Test |
| P1 | Var | MSB of card object size |
| P2 | Var | LSB of card object size |
| Lc | Var | Nc encoded in short or extended format |
| C-Data | Var | Arbitrary data with the length encoded in Nc |
| Le | Var | Ne encoded in short or extended format |
| R-Data | Var | The requested number of bytes which is a repeating sequence of the bytes 'A55A0000FFFFCAFEBABE" |
| SW1/2 | '90 00' | Normal processing |
| | '67 00' | Wrong length |
| | '6A 86' | Incorrect parameters P1-P2 |

Table 8 - Case 4 Test APDU

- /FR.CAS4.1/ The system must accept arbitrary data in C-Data and respond with the requested number of bytes in R-Data and SW1/SW2 = '90 00' Normal processing.
- /FR.CAS4.2/ If Ne is not 0 and requests more data than is actually available based on the definition in P1 and P2, then the system must respond with the available data in R-Data and SW1/SW2 = '62 82' End of file reached before reading Ne bytes.

3.1.5.1 Exception Handling

- /FX.CAS4.1/ If the C-Data field is missing, then the system must respond with empty R-Data and SW1/SW2 = '67~00' Wrong length.
- /FX.CAS4.3/ If the number of bytes transmitted in C-Data field does match Nc, then the system must respond with empty R-Data and SW1/SW2 = '6A 80' Incorrect parameters in the command data field.

3.1.6 GET INFO

The GET INFO command returns information about the last APDU processed.



| CLA | '80' | |
|--------|---------|---|
| INS | 'F0' | GET INFO |
| P1 | '00' | |
| P2 | '00' | |
| Lc | Absent | |
| C-Data | Absent | |
| Le | '00' | |
| R-Data | Var | A sequence of information bytes reflecting the processing of the last APDU as defined in Table 10 |
| SW1/2 | '90 00' | Normal processing |
| | '67 00' | Wrong length |
| | '6A 86' | Incorrect parameters P1-P2 |

Table 9 - GET INFO APDU

| Offset | Length | Content |
|--------|--------|----------------|
| 0 | 1 | CLA |
| 1 | 1 | INS |
| 2 | 1 | P1 |
| 3 | 1 | P2 |
| 4 | 2 | Nc requested |
| 6 | 2 | Nc received |
| 8 | 2 | Ne requested |
| 10 | 2 | Ne transmitted |

Table 10 - GET INFO R-Data

/FR.INFO.1/ The system must respond with the information about the last processed test APDU in R-Data and SW1/SW2 = '90 00' - Normal processing.

3.1.6.1 Exception Handling

/FX.INFO.1/ If the C-Data field is present, then the system must respond with empty R-Data and SW1/SW2 = '67 00' - Wrong length.

/FX.INFO.2/ If the Ne field does not encode 0 or 12, then the system must respond with empty R-Data and SW1/SW2 = '67 00' - Wrong length.

References

[ISO7816-3] Information Technology – Identification card – Integrated circuit(s) card with contacts – Part 3: Electronic signals and transmission protocols.

Andreas Schwier 9 / 9